

Maria-DB & MySQL

Table of Contents

1. How to install	1
2. How to configure	1
2.1. Make it accessable from everywhere.....	1
2.2. Restart MYSQL-database.....	2
3. Basic MySQL statements for configuration	2
3.1. Enter MariaDB-Monitor	2
3.2. Exit MariaDB-Monitor	2
3.3. Create user	2
3.4. Create user if not exists.....	2
3.5. User grants	2
3.6. Delete user	2
4. Connect Maria-DB to Data-Grip.....	2
4.1. Select Maria-DB.....	2
4.2. Configure	2
5. Database commands in Data-Grip	3
5.1. Create database.....	3
5.2. Drop database	3
5.3. SELECT database to use it.....	4
6. Insight View: Code Snippet.....	4

1. How to install

```
sudo apt install mariadb-server
```

```
sudo mysql_secure_installation
```

```
-y,-y,-y,-y''
```

2. How to configure

2.1. Make it accessable from everywhere

```
sudo nano /etc/mysql/mariadb.conf.d/50-server.cnf
```

- **Methode One:**

- `bind-adress = 0.0.0.0`

- **Methode Two:**

- bind-adress = stevan.ddns.net

2.2. Restart MYSQL-database

```
sudo service mysql restart
```

3. Basic MySQL statements for configuration

3.1. Enter MariaDB-Monitor

```
sudo mysql
```

3.2. Exit MariaDB-Monitor

```
exit
```

3.3. Create user

```
CREATE USER 'username'@'%' IDENTIFIED BY 'password';
```

3.4. Create user if not exists

```
CREATE USER IF NOT EXISTS 'user'@'%' IDENTIFIED BY 'password';
```

```
CREATE USER IF NOT EXISTS 'user'@'localhost' IDENTIFIED BY 'password';
```

3.5. User grants

```
GRANT ALL PRIVILEGES ON . TO 'username'@'%' WITH GRANT OPTION;
```

```
GRANT ALL PRIVILEGES ON . TO 'username'@'localhost' WITH GRANT OPTION;
```

3.6. Delete user


```
DROP USER 'username'@'%';
```

```
DROP USER 'username'@'localhost';
```

4. Connect Maria-DB to Data-Grip

4.1. Select Maria-DB


4.2. Configure



5. Database commands in Data-Grip

5.1. Create database

```
CREATE DATABASE myDatabase_name;
```



5.2. Drop database

```
DROP DATABASE myDatabase_name;
```

5.3. SELECT database to use it

```
use myDatabase_name;
```

6. Insight View: Code Snippet

```
1  CREATE DATABASE myDatabase_name;
2  use test;
3
4  create table test (
5      name char(20),
6      rfid int(20)
7  );
8
9  insert into test (name, rfid) values('Stevan', 927466);
10 insert into test (name, rfid) values('Jonas', 924466);
11 insert into test (name, rfid) values('Tobias', 924443);
12
13 select * from test;
```